

# CBP350 Ocean Customs Status Information

August 2024



U.S. Customs and  
Border Protection



## Table of Changes

Revision Number	Date of Change	Section(s) Affected	Brief Description of Change
1.02	8/29/2024	M1002 Type Code	Added VE – Un-Containerized Type Code to M1002

# 350 Customs Status Information

Functional Group ID=**SO**

## Introduction:

This X12 Transaction Set contains the format and establishes the data contents of the Customs Status Information Transaction Set (350) for use within the context of an Electronic Data Interchange (EDI) environment. The transaction set can be used by the Customs Service (CS) to supply carriers, terminal operators, port authorities and service providers with cargo release and cargo hold information for import shipments. It can also be used by the CS to provide exporters or their agents, carriers, and service providers with information pertaining to export shipments.

This Implementation Guideline uses the ASC X12 6050 Standards Version/Release as its base. The transaction structure has been altered to accommodate U.S. Customs and Border Protection implementation requirements.

## Notes:

All transactions will result in a new status notification which will be sent to all parties associated with the manifest.

### Notes:

1. The X4 segment is provided for Bill of Lading status notifications.
2. The V9 segment is provided for conveyance-level status notifications.

The first occurrence of any of the X415 reference qualifiers 8S (Future Use), OB, or BN is reported on the X4 segment. If more than one of these applies, additional values are reported on the Reference Identifier segment (N9). A Secondary Notify Party (SNP) can only be reported using the N9 segment.

### Special Messaging constraints:

- Limit one Interchange (ISA-IEA) per message transmission is required
- Limit one message Group (GS-GE) per message transmission is required
- Limit one transaction set (ST-SE) of the same Transaction Set Identifier (TS) Code (i.e., 350). Only one is allowed per message transmission.
- Element delimiters used in this transaction will be '\*' (asterisk). No blanks between delimiters if element is null.
- Segment delimiters used in this transaction will be one byte with a value of hex '15'.
- A segment delimiter will be the last byte of data in the message transmission data stream.
- Only uppercase AMERICAN ENGLISH alphabetic data will be transmitted.
- ONLY displayable characters found on a standard American English keyboard will be transmitted. Low-values, carriage return characters, or other non-standard characters shall NOT be transmitted.
- 'Not Used' in the left column indicates that a composite or data element will not be used by CBP.
- 'Dep' in the left column indicates that CBP usage of a particular segment or element is Dependent (Conditional) within the CBP application.
- Per the ASC X12 Standard, an 'M' indicates a Mandatory use, 'O' indicates Optional Use and an 'X' indicates a Conditional use.
- CBP requirements may override ASC X12 Standard Mandatory or Conditional usages.
- Maximum allowable message transmission size is 12 megabytes (12,582,912 bytes) of data.

(Last Update: January 2015) ACE v 1.0 Ocean export

	<u>Pos. No.</u>	<u>Seg. ID</u>	<u>Name</u>	<u>Req. Des.</u>	<u>Max.Use</u>	<u>Loop Repeat</u>
M	0050	ISA	Interchange Control Header	M	1	
M	0075	GS	Functional Group Header	M	1	
M	0100	ST	Transaction Set Header	M	1	
M	0200	M10	Manifest Identifying Information	O	1	
LOOP ID - P4						20
M	0400	P4	Port Information	O	1	
DEP	0450	V9	Event Detail	O	20	
Not Used	0460	VEH	Vehicle Information	O	10	

Not Used	0465	NM1	Individual or Organizational Name	O	9999
					9999
DEP	0470	VID	Conveyance Identification	O	1
DEP	0480	M7	Seal Numbers	O	5
DEP	0490	M7A	Seal Number Replacement	O	22
Not Used	0500	K1	Remarks	O	4
			LOOP ID - X4		9999
			Customs Release Information	O	1
			Remarks	O	4
DEP	0600	X4	Extended Reference Information	O	999
DEP	0700	K1	Equipment Details	O	999
DEP	0710	N9			
DEP	0810	N7	LOOP ID - BA1		999
			Export Shipment Identifying Information	O	1
			LOOP ID - X4		9999
			Customs Release Information	O	1
Not Used	0850	BA1	Remarks	O	4
Not Used	0900	X4			
Not Used	0950	K1			
M	1000	SE	Transaction Set Trailer	M	1
M	1050	GE	Functional Group Trailer	M	1
M	1100	IEA	Interchange Control Trailer	M	1

**Segment:** **ISA** Interchange Control Header  
**Position:** 0050  
**Loop:**  
**Level:**  
**Usage:** Mandatory  
**Max Use:** 1  
**Purpose:** To start and identify an interchange of zero or more functional groups and interchange-related control segments

**Syntax Notes:**  
**Semantic Notes:**

Data Element Summary				
Ref.	Data			
	<u>Des.</u>	<u>Element</u>	<u>Name</u>	<u>Attributes</u>
M	ISA01	I01	<b>Authorization Information Qualifier</b> Code identifying the type of information in the Authorization Information Always '00' 00 No Authorization Information Present (No Meaningful Information in I02)	M 1 ID 2/2
M	ISA02	I02	<b>Authorization Information</b> Information used for additional identification or authorization of the interchange sender or the data in the interchange; the type of information is set by the Authorization Information Qualifier (I01) Always 10 spaces.	M 1 AN 10/10
M	ISA03	I03	<b>Security Information Qualifier</b> Code identifying the type of information in the Security Information Always '00' 00 No Security Information Present (No Meaningful Information in I04)	M 1 ID 2/2
M	ISA04	I04	<b>Security Information</b> This is used for identifying the security information about the interchange sender or the data in the interchange; the type of information is set by the Security Information Qualifier (I03) Always 10 spaces.	M 1 AN 10/10
M	ISA05	I05	<b>Interchange ID Qualifier</b> Code indicating the system/method of code structure used to designate the sender or receiver ID element being qualified Always 'ZZ' ZZ Mutually Defined	M 1 ID 2/2
M	ISA06	I06	<b>Interchange Sender ID</b> Identification code published by the sender for other parties to use as the receiver ID to route data to them; the sender always codes this value in the sender ID element CUSTOMSTST Testing CUSTOMS Production	M 1 AN 15/15
M	ISA07	I05	<b>Interchange ID Qualifier</b> Code indicating the system/method of code structure used to designate the sender or receiver ID element being qualified Always 'ZZ' ZZ Mutually Defined	M 1 ID 2/2
M	ISA08	I07	<b>Interchange Receiver ID</b> Identification code published by the receiver of the data; When sending, it is used by the sender as their sending ID, thus other parties sending to them will use this as a receiving ID to route data to them	M 1 AN 15/15

			Receiver Identifier. Up to 4 alpha-numeric characters. Value will contain the Standard Carrier Alpha Code (SCAC) or the identity of the Service Center if applicable. May be identical to that of GS03.		
M	ISA09	I08	<b>Interchange Date</b>	M	1 DT 6/6
			Date of the interchange		
			Date as YYMMDD where:		
			YY	Year	
			MM	Month of Year	
			DD	Day of Month	
M	ISA10	I09	<b>Interchange Time</b>	M	1 TM 4/4
			Time of the interchange		
			Time as HHMM where:		
			HH	Hour	
			MM	Minute	
M	ISA11	I65	<b>Repetition Separator</b>	M	1 AN 1/1
			Type is not applicable; the repetition separator is a delimiter and not a data element; this field provides the delimiter used to separate repeated occurrences of a simple data element or a composite data structure; this value must be different than the data element separator, component element separator, and the segment terminator		
			Repetition Separator = “^” (caret)		
M	ISA12	I11	<b>Interchange Control Version Number Code</b>	M	1 ID 5/5
			Code specifying the version number of the interchange control segments		
			Always '00605'		
			00605	Standards Approved for Publication by ASC X12 Procedures Review Board through October 2013	
M	ISA13	I12	<b>Interchange Control Number</b>	M	1 N0 9/9
			A control number assigned by the interchange sender		
M	ISA14	I13	<b>Acknowledgment Requested Code</b>	M	1 ID 1/1
			Code indicating sender's request for an interchange acknowledgment		
			Always '0'		
			0	No Interchange Acknowledgment Requested	
M	ISA15	I14	<b>Interchange Usage Indicator Code</b>	M	1 ID 1/1
			Code indicating whether data enclosed by this interchange envelope is test, production or information		
			Always 'P' or 'T'		
			P	Production Data	
			T	Test Data	
M	ISA16	I15	<b>Component Element Separator</b>	M	1 AN 1/1
			Type is not applicable; the component element separator is a delimiter and not a data element; this field provides the delimiter used to separate component data elements within a composite data structure; this value must be different than the data element separator and the segment terminator		
			Always ':' (colon)		

**Segment:** **GS** Functional Group Header  
**Position:** 0075  
**Loop:**  
**Level:**  
**Usage:** Mandatory  
**Max Use:** 1  
**Purpose:** To indicate the beginning of a functional group and to provide control information  
**Syntax Notes:**  
**Semantic Notes:**

- 1 GS04 is the group date.
- 2 GS05 is the grouptime.
- 3 The data interchange control number GS06 in this header must be identical to the same data element in the associated functional group trailer, GE02.

Data Element Summary				
Ref.	Data			
	<u>Des.</u>	<u>Element</u>	<u>Name</u>	<u>Attributes</u>
M	GS01	479	<b>Functional Identifier Code</b> Code identifying a group of application related transaction sets Always 'SO'	M 1 ID 2/2
			SO Ocean Shipment Information	
M	GS02	142	<b>Application Sender's Code</b> Code identifying party sending transmission; codes agreed to by trading partners CUSTOMSTST Testing CUSTOMS Production	M 1 AN 2/15
M	GS03	124	<b>Application Receiver's Code</b> Code identifying party receiving transmission; codes agreed to by trading partners Receiver Identifier. Up to 4 alpha/numeric characters. Value will contain the Standard Carrier Alpha Code (SCAC) or the identity of the Service Center if applicable. May be identical to that of ISA08.	M 1 AN 2/15
M	GS04	373	<b>Date</b> Date expressed as CCYYMMDD where CC represents the first two digits of the calendar year Date as CCYYMMDD where : CC Century DD Day of Month MM Month of Year YY Year	M 1 DT 8/8
M	GS05	337	<b>Time</b> Time expressed in 24-hour clock time as follows: HHMM, or HHMMSS, or HHMMSSD, or HHMMSSDD, where H = hours (00-23), M = minutes (00-59), S = integer seconds (00-59) and DD = decimal seconds; decimal seconds are expressed as follows: D = tenths (0-9) and DD = hundredths (00-99) Eastern Standard/Daylight Time used. Time as HHMM where: HH Hour MM Minute	M 1 TM 4/8
M	GS06	28	<b>Group Control Number</b> Assigned number originated and maintained by the sender	M 1 N0 1/9
M	GS07	455	<b>Responsible Agency Code</b> Code identifying the issuer of the standard; this code is used in conjunction with Data Element 480 Always 'X' X Accredited Standards Committee X12	M 1 ID 1/2

<b>M</b>	<b>GS08</b>	<b>480</b>	<b>Version / Release / Industry Identifier Code</b>	<b>M</b>	<b>1 AN 1/12</b>
			Code indicating the version, release, sub release, and industry identifier of the EDI standard being used, including the GS and GE segments; if code in DE455 in GS segment is X, then in DE 480 positions 1-3 are the version number; positions 4-6 are the release and sub release, level of the version; and positions 7-12 are the industry or trade association identifiers (optionally assigned by user); if code in DE455 in GS segment is T, then other formats are allowed		
			Always '006050'		
			006050	Standards Approved for Publication by ASC X12 Procedures Review Board through October 2013	



<b>Segment:</b>	<b>ST</b>	<b>Transaction Set Header</b>
<b>Position:</b>	0100	
<b>Loop:</b>		
<b>Level:</b>		
<b>Usage:</b>	Mandatory	
<b>Max Use:</b>	1	
<b>Purpose:</b>	To indicate the start of a transaction set and to assign a control number	
<b>Syntax Notes:</b>		
<b>Semantic Notes:</b>	<ol style="list-style-type: none"> <li>1 The transaction set identifier (ST01) is used by the translation routines of the interchange partners to select the appropriate transaction set definition (e.g., 810 selects the Invoice Transaction Set).</li> <li>2 The implementation convention reference (ST03) is used by the translation routines of the interchange partners to select the appropriate implementation convention to match the transaction set definition. When used, this implementation convention reference takes precedence over the implementation reference specified in the GS08.</li> </ol>	

Data Element Summary				
Ref.	Data			
	<u>Des.</u>	<u>Element</u>	<u>Name</u>	<u>Attributes</u>
M	ST01	143	Transaction Set Identifier Code Code identifying a Transaction Set Always '350'	M 1 ID 3/3
		350	Customs Status Information	
M	ST02	329	Transaction Set Control Number Identifying control number that must be unique within the transaction set functional group assigned by the originator for a transaction set	M 1 AN 4/9
Not Used	ST03	1705	Implementation Convention Reference	O 1 AN 1/35

<b>Segment:</b>	<b>M10</b>	<b>Manifest Identifying Information</b>
<b>Position:</b>	0200	
<b>Loop:</b>		
<b>Level:</b>		
<b>Usage:</b>	Optional	
<b>Max Use:</b>	1	
<b>Purpose:</b>	To transmit manifest identifying information	
<b>Syntax Notes:</b>	1	If either M1004 or M1010 is present, then the other is required.
	2	If either M1015 or M1016 is present, then the other is required.
	1	M1004 is the International Maritime Organization (IMO) Vessel Code maintained in Lloyd's Register of Shipping.
	2	M1007 is used for the six-digit Numeric Manifest Sequence Number.
	3	M1011 indicates if the transmission involves an in-bond participant. A "Y" indicates it does; an "N" indicates it does not.
<b>Semantic Notes:</b>	4	M1012 is a unique identification number for the manifest assigned by the originator of the manifest with a maximum length of 15.
	5	M1017 is the type of initial manifest being amended by this transmission.
	1.	M1003 is the code identifying the country in which the ship (vessel) is registered.
	2.	M1008 is used for number of bills lading (maximum five digits).
<b>Notes:</b>		

#### Data Element Summary

Ref.	Data			
	<u>Des.</u>	<u>Element</u>	<u>Name</u>	<u>Attributes</u>
M	M1001	140	<b>Standard Carrier Alpha Code</b> Code identifying the Standard Carrier Alpha Code SCAC of Carrier initiating the export manifest.	M 1 ID 2/4
M	M1002	91	<b>Transportation Method/Type Code</b> Code specifying the method or type of transportation for the shipment Code specifying the methods or type of transportation for the shipment. O Containerized Ocean VE Un-Containerized	M 1 ID 1/2
M	M1003	26	<b>Country Code</b> Code identifying the country SO 2 alpha Country Code from inbound manifest.	M 1 ID 2/3
DEP	M1004	597	<b>Vessel Code</b> Code Identifying the vessel IMO code for vessel – 7 numeric characters.	X 1 ID 1/8
	M1005	182	<b>Vessel Name</b> Name of ship as documented in "Lloyd's Register of Ships" BP returns up to 23 alpha/numeric characters in this element.	O 1 AN 2/28
M	M1006	55	<b>Flight/Voyage Number</b> Identifying designator for the particular flight or voyage on which the cargo travels CBP provides the voyage number included in the original manifest.	O 1 AN 2/30
M	M1007	127	<b>Reference Identification</b> Reference information as defined for a particular Transaction Set or as specified by the Reference Identification Qualifier Unique carrier number is provided by CBP in the notification. If not provided, CBP will return '000001' in the notification message.	O 1 AN 1/80
Not Used	M1008	380	<b>Quantity</b>	O 1 R 1/15
M	M1009	256	<b>Manifest Type Code</b> Code identifying the type of manifest transmitted Always 'Z' Z Sent from U.S. Customs to Carriers	O 1 ID 1/1
	M1010	897	<b>Vessel Code Qualifier</b> Code specifying the vessel code source Value will be returned if sent in the original 309 set L International Maritime Organization	X 1 ID 1/1

Not Used	M1011	1073	Yes/No Condition or Response Code	O	1 ID 1/1
Not Used	M1012	127	Reference Identification	O	1 AN 1/80
Not Used	M1013	353	Transaction Set Purpose Code	O	1 ID 2/2
	M1014	346	Application Type Code	O	1 ID 2/2
			Code identifying an operation		
			Value accepted by CBP:		
		22	Ocean Export Manifest		
Not Used	M1015	580	Amendment Type Code	X	1 ID 1/1
Not Used	M1016	393	Amendment Code	X	1 ID 2/2
Not Used	M1017	256	Manifest Type Code	O	1 ID 1/1

<b>Segment:</b>	<b>P4 Port Information</b>
<b>Position:</b>	0400
<b>Loop:</b>	P4 Optional
<b>Level:</b>	
<b>Usage:</b>	Optional
<b>Max Use:</b>	1
<b>Purpose:</b>	To transmit identifying information for a port
<b>Syntax Notes:</b>	
<b>Semantic Notes:</b>	<ol style="list-style-type: none"> <li>1 P401 is used for customs district and port code (census schedule D).</li> <li>2 P402 is the estimated date of arrival.</li> <li>3 P403 is used for number of bills of lading.</li> <li>4 P404 is the Facilities Information and Resources Management System (FIRMS) Code.</li> <li>5 P405 is the estimated time of arrival for P402.</li> <li>6 P406 is the date conveyance departed prior port.</li> <li>7 P407 is the time conveyance departed prior port.</li> </ol>

Data Element Summary					
	Ref.	Data			
	<u>Des.</u>	<u>Element</u>	<u>Name</u>	<u>Attributes</u>	
M	P401	310	<b>Location Identifier</b> Code which identifies a specific location When M1002 = 'O', CBP provides the Port of Departure of the vessel from the U.S.	M	1 AN 1/30
M	P402	373	<b>Date</b> Date expressed as CCYYMMDD where CC represents the first two digits of the calendar year Estimated Date of Departure from the port in P401 CC Century DD Day of Month MM Month of Year YY Year	M	1 DT 8/8
Not Used	P403	380	<b>Quantity</b>	O	1 R 1/15
Required	P404	310	<b>Location Identifier</b> Code which Identifie a specific location In a vessel coastwise movement this is the next US port of call after the port in 401. In the last port of call prior to departure from the U , this is the first foreign port of destination. - For US ports of ca 1 CBP only accepts 4 numeric Characters in this field (Census Schedule D) - For the first foreig n port CBP only accepts 5 numeric Characters in this field (Census Schedule K)	O	1 AN 1/30
Not Used	P405	337	<b>Time</b>	O	1 TM 4/8
Not Used	P406	373	<b>Date</b>	O	1 DT 8/8
Not Used	P407	337	<b>Time</b>	O	1 TM 4/8

<b>Segment:</b>	<b>V9</b> Event Detail
<b>Position:</b>	0450
<b>Loop:</b>	P4 Optional
<b>Level:</b>	
<b>Usage:</b>	Optional
<b>Max Use:</b>	20
<b>Purpose:</b>	To specify information about a specific event
<b>Syntax Notes:</b>	<b>1</b> If V906 is present, then V905 is required. <b>2</b> If either V910 or V911 is present, then the other is required. <b>3</b> If V913 is present, then V904 is required. <b>4</b> If V915 is present, then V909 is required.
<b>Semantic Notes:</b>	<b>1</b> V903 is the event date. <b>2</b> V904 is the event time. <b>3</b> V909 is the Standard Point Location Code (SPLC) of the event shown in the V901. <b>4</b> V910 is the length of the time delay expressed in hours. <b>5</b> V913 reflects the time zone which the event time reflects. <b>6</b> V914 is the quantity of the fuel in gallons. <b>7</b> V915 is the Standard Point Location Code (SPLC) of the secondary point of the delay indicated in the V911. <b>8</b> V916 is the total number of rail cars associated with the event code in V901. <b>9</b> V917 is the total number of loaded cars associated with the event code in V901. <b>10</b> V918 is the total number of empty cars associated with the event code in V901. <b>11</b> V919 is the total Gross Tons of the cars identified in V916. Includes the gross weight of the loads and the tare weight of the empties. <b>12</b> V920 is the total outside foot length of the cars identified in V916, rounded off to the nearest foot.
<b>Notes:</b>	This segment will be provided when CBP arrives a vessel and notifies the carrier. Will also be sent to notify the carrier that the vessel arrival is overdue, held or released.

#### Data Element Summary

Ref.	Data				
	<u>Des.</u>	<u>Element</u>	<u>Name</u>		<u>Attributes</u>
M	V901	304	Event Code	M	1 ID 3/3
			Code identifying the event about which a report is made		
			Values provided by CBP.		
			AAD	Actual Arrival of conveyance in port of load	
			CDE	Conveyance departure from U.S. - export	
			CDI	Conveyance departure from foreign port - import	
			COC	Cancellation of Conveyance arrival.	
				This capability is restricted to the most recent arrival of a vessel in a port of departure and can only be performed by CBP personnel via the portal.	
				This cancellation will negate the arrivals/exports of inbounds associated with the vessel/voyage that have occurred after the vessel has arrived in the port.	
			HMI	Hold or Miscellaneous	
			HRE	Release from Hold or Miscellaneous	
			OCA	Overdue Conveyance Arrival	
			SEI	Seized Equipment	
			SER	Seized Equipment - Removed	
Not Used	V902	106	Event	O	1 AN 1/25
	V903	373	Date	O	1 DT 8/8
			Date expressed as CCYYMMDD where CC represents the first two digits of the calendar year		
			Date of Posting.		
			Date as CCYYMMDD where:		
			CC	Century	
			DD	Day of Month	

			MM	Month of Year					
			YY	Year					
	<b>V904</b>	<b>337</b>	<b>Time</b>			<b>X</b>	<b>1</b>	<b>TM 4/8</b>	
			Time expressed in 24-hour clock time as follows: HHMM, or HHMMSS, or HHMMSSD, or HHMMSSDD, where H = hours (00-23), M = minutes (00-59), S = integer seconds (00-59) and DD = decimal seconds; decimal seconds are expressed as follows: D = tenths (0-9) and DD = hundredths (00-99)						
			Time of Posting will be in Eastern Standard/Daylight time.						
			Time as HHMM where:						
			HH	Hour					
			MM	Minute					
Not Used	<b>V905</b>	<b>19</b>	<b>City Name</b>			<b>X</b>	<b>1</b>	<b>AN 2/30</b>	
Not Used	<b>V906</b>	<b>156</b>	<b>State or Province Code</b>			<b>O</b>	<b>1</b>	<b>ID 2/2</b>	
Not Used	<b>V907</b>	<b>26</b>	<b>Country Code</b>			<b>O</b>	<b>1</b>	<b>ID 2/3</b>	
Not Used	<b>V908</b>	<b>641</b>	<b>Status Reason Code</b>			<b>O</b>	<b>1</b>	<b>ID 3/3</b>	
Not Used	<b>V909</b>	<b>154</b>	<b>Standard Point Location Code</b>			<b>X</b>	<b>1</b>	<b>ID 6/9</b>	
Not Used	<b>V910</b>	<b>380</b>	<b>Quantity</b>			<b>X</b>	<b>1</b>	<b>R 1/15</b>	
Not Used	<b>V911</b>	<b>1274</b>	<b>Train Delay Reason Code</b>			<b>X</b>	<b>1</b>	<b>AN 2/3</b>	
Not Used	<b>V912</b>	<b>61</b>	<b>Free-form Information</b>			<b>O</b>	<b>1</b>	<b>AN 1/30</b>	
Not Used	<b>V913</b>	<b>623</b>	<b>Time Code</b>			<b>O</b>	<b>1</b>	<b>ID 2/2</b>	
Not Used	<b>V914</b>	<b>380</b>	<b>Quantity</b>			<b>O</b>	<b>1</b>	<b>R 1/15</b>	
Not Used	<b>V915</b>	<b>154</b>	<b>Standard Point Location Code</b>			<b>O</b>	<b>1</b>	<b>ID 6/9</b>	
Not Used	<b>V916</b>	<b>86</b>	<b>Total Equipment</b>			<b>O</b>	<b>1</b>	<b>N0 1/3</b>	
Not Used	<b>V917</b>	<b>86</b>	<b>Total Equipment</b>			<b>O</b>	<b>1</b>	<b>N0 1/3</b>	
Not Used	<b>V918</b>	<b>86</b>	<b>Total Equipment</b>			<b>O</b>	<b>1</b>	<b>N0 1/3</b>	
Not Used	<b>V919</b>	<b>81</b>	<b>Weight</b>			<b>O</b>	<b>1</b>	<b>R 1/10</b>	
Not Used	<b>V920</b>	<b>82</b>	<b>Length</b>			<b>O</b>	<b>1</b>	<b>R 1/8</b>	

<b>Segment:</b>	<b>VID</b>	<b>Conveyance Identification</b>
<b>Position:</b>	0470	
<b>Loop:</b>	VID	Optional
<b>Level:</b>		
<b>Usage:</b>	Optional	
<b>Max Use:</b>	1	
<b>Purpose:</b>	To identify a conveyance and its attributes	
<b>Syntax Notes:</b>	<b>1</b> If VID14 is present, then at least one of VID15 or VID18 is required. <b>2</b> Only one of VID15 or VID18 may be present. <b>3</b> If VID15 is present, then VID16 is required. <b>4</b> If VID16 is present, then at least one of VID15 or VID18 is required. <b>5</b> If VID18 is present, then VID16 is required.	
<b>Semantic Notes:</b>	<b>1</b> VID12 is the Census Schedule K code for the foreign port of loading on a vessel. <b>2</b> VID13 is the Standard Carrier Alpha Code (SCAC) of the Haulage Rights Carrier. <b>3</b> VID14 is the license plate of the equipment. <b>4</b> VID15 is the state or province of the license in the VID14. <b>5</b> VID16 is the country of the license in the VID15 or VID18. <b>6</b> VID17 is the ACE (Automated Commercial Environment) ID of the equipment identified in the VID03. <b>7</b> VID18 is the country subdivision of the license in the VID14.	
<b>Notes:</b>	VID will only be generated outbound if V901 is 'HMT', 'HRE', 'SEI', or 'SER' and the action is against an empty container on the Consist.	

Data Element Summary					
Ref.	Data				
	<u>Des.</u>	<u>Element</u>	<u>Name</u>	<u>Attributes</u>	
M	VID01	40	<b>Equipment Description Code</b> Code identifying type of equipment used for shipment Refer to Export Multimodal Manifest Appendix F.	M	1 ID 2/2
	VID02	206	<b>Equipment Initial</b> Prefix or alphabetic part of an equipment unit's identifying number For containers without initials:'NONU'.	O	1 AN 1/4
M	VID03	207	<b>Equipment Number</b> Sequencing or serial part of an equipment unit's identifying number (pure numeric form for equipment number is preferred)	M	1 AN 1/15
Not Used	VID04	225	<b>Seal Number</b>	O	1 AN 2/15
Not Used	VID05	225	<b>Seal Number</b>	O	1 AN 2/15
	VID06	567	<b>Equipment Length</b> Length (in feet and inches) of equipment ordered or used to transport a shipment. (the format is FFFII where FFF is feet and II is inches; the range for II is 00 through II) This value will be returned when sent in the original manifest	O	1 N0 4/5
	VID07	65	<b>Height</b> Vertical dimension of an object measured when the object is in the upright position This value will be returned when sent in the original manifest.	O	1 R 1/8
	VID08	189	<b>Width</b> Shorter measurement of the two horizontal dimensions measured with the object in the upright position This value will be returned when sent in the original manifest.	O	1 R 1/8
Not Used	VID09	24	<b>Equipment Type Code</b>	O	1 ID 4/4
	VID10	322	<b>Load/Empty Status Code</b> Code which specifies the loaded condition of transportation equipment This value will be returned when sent in the original manifest.	O	1 ID 1/1

			E L	Empty Loaded			
	VID11	56	Type of Service Code			O	1 ID 2/2
Not Used	VID12	310	Location Identifier			O	1 AN 1/30
	VID13	140	Standard Carrier Alpha Code			O	1 ID 2/4
			Code identifying the Standard Carrier Alpha Code				
			Owner of Equipment LessorSCAC.				
Not Used	VID14	127	Reference Identification			O	1 AN 1/80
Not Used	VID15	156	State or Province Code			X	1 ID 2/2
Not Used	VID16	26	Country Code			X	1 ID 2/3
Not Used	VID17	127	Reference Identification			O	1 AN 1/80
Not Used	VID18	1715	Country Subdivision Code			X	1 ID 1/3
Not Used	VID19	512	Import/Export Code			O	1 ID 1/1
Not Used	VID20	761	Equipment Number Check Digit			O	1 N0 1/1



**Segment:** **M7** Seal Numbers  
**Position:** 0480  
**Loop:** VID Optional  
**Level:**  
**Usage:** Optional  
**Max Use:** 5  
**Purpose:** To record seal numbers used and the organization that applied the seals  
**Syntax Notes:**  
**Semantic Notes:**

Data Element Summary				
	Ref.	Data		
	<u>Des.</u>	<u>Element</u>	<u>Name</u>	<u>Attributes</u>
M	M701	225	Seal Number	M 1 AN 2/15
			Unique number on seal used to close a shipment	
			A valid exporter/carrier seal number associated with this shipment. Cannot include " . " or " - ". Required by CBP for rail usage if additional seals are applied.	
	M702	225	Seal Number	O 1 AN 2/15
			Unique number on seal used to close a shipment	
			A valid exporter/carrier seal number associated with this shipment. Cannot include " . " or " - ". Required by CBP for rail usage if additional seals are applied.	
	M703	225	Seal Number	O 1 AN 2/15
			Unique number on seal used to close a shipment	
			A valid exporter/carrier seal number associated with this shipment. Cannot include " . " or " - ". Required by CBP for rail usage if additional seals are applied.	
	M704	225	Seal Number	O 1 AN 2/15
			Unique number on seal used to close a shipment	
			A valid exporter/carrier seal number associated with this shipment. Cannot include " . " or " - ". Required by CBP for rail usage if additional seals are applied.	
Not Used	M705	98	Entity Identifier Code	O 1 ID 2/3

**Segment:** M7A Seal Number Replacement  
**Position:** 0490  
**Loop:** VID Optional  
**Level:**  
**Usage:** Optional  
**Max Use:** 22  
**Purpose:** To provide an audit trail of seal number changes  
**Syntax Notes:** 1 If either M7A04 or M7A05 is present, then the other is required.  
**Semantic Notes:** 1 M7A01 is the original seal number.  
2 M7A02 is the replacement seal number.  
3 M7A03 is the date the new seal was installed.  
4 M7A04 and M7A05 indicate the party responsible for the seal replacement.  
5 M7A06 is a description of why the seal was replaced.  
6 M7A07 is the location of the replaced seal on the equipment.

Data Element Summary					
Ref.	Data				
	<u>Des.</u>	<u>Element</u>	<u>Name</u>	<u>Attributes</u>	
M	M7A01	225	Seal Number	M	1 AN 2/15
			Unique number on seal used to close a shipment		
			A valid exporter/carrier seal number associated with this shipment. If it is a seal number it must be provided. It cannot include special Characters ('.', '-', '/', etc.)		
			This is the seal that is being replaced		
M	M7A02	225	Seal Number	M	1 AN 2/15
			Unique number on seal used to close a shipment		
			A valid exporter/carrier seal number associated with this shipment. If it is a seal number it must be provided. It cannot include special Characters ('.', '-', '/', etc.)		
			This is the seal replacing the seal listed in M7A01		
	M7A03	373	Date	O	1 DT 8/8
			Date expressed as CCYYMMDD where CC represents the first two digits of the calendar year		
			The date the change of seal occurred		
			Date as CCYYMMDD where:		
			CC Century		
			DD Day of Month		
			MM Month of Year		
			YY Year		
Not Used	M7A04	98	Entity Identifier Code	X	1 ID 2/3
	M7A05	93	Name	X	1 AN 1/60
			Free-form name		
	M7A06	352	Description	O	1 AN 1/80
			A free-form description to clarify the related data elements and their content		
			Reason for the change of seal.		
	M7A07	302	Location on Equipment Code	O	1 ID 1/3
			Code indicating a location on a piece of equipment, as observed from the rear-end. The rear-end of the equipment is based on the equipment type (i.e. container door, chassis wheels, brakes.)		
			Codes accepted by CBP:		
			C Complete Equipment, Right and Left		
			F Front		
			I Interior		
			LF Left Front		
			LIC Left Inner Center		
			LIF Left Inside Front		

LIR	Left Inside Rear
LOC	Left Outer Center
LOF	Left Outside Front
LOR	Left Outside Rear
LR	Left Rear
LS	Left Side
R	Rear
ROF	Right Outside Front
RF	Right Front
RIC	Right Inner Center
RIF	Right Inside Front
ROC	Right Outer Center
ROR	Right Outside Rear
RR	Right Rear
RS	Right Side
RSC	Right Side Center
RSF	Right Side Front
RSR	Right Side Rear
T	Top
TC	Top Center
TF	Top Front
TR	Top Rear
U	Under

<b>Segment:</b>	<b>X4 Customs Release Information</b>
<b>Position:</b>	0600
<b>Loop:</b>	X4 Optional
<b>Level:</b>	
<b>Usage:</b>	Optional
<b>Max Use:</b>	1
<b>Purpose:</b>	To identify items for release
<b>Syntax Notes:</b>	<ol style="list-style-type: none"> <li>1 If either X403 or X404 is present, then the other is required.</li> <li>2 If either X408 or X410 is present, then the other is required.</li> <li>3 If either X415 or X416 is present, then the other is required.</li> <li>4 If X417 is present, then X406 is required.</li> <li>5 If X418 is present, then X403 is required.</li> <li>6 If X419 is present, then X403 is required.</li> </ol>
<b>Semantic Notes:</b>	<ol style="list-style-type: none"> <li>1 X401 is the unique bill of lading number.</li> <li>2 X402 is used for quantity released.</li> <li>3 X405 is the date that the disposition code was posted to Customs file.</li> <li>4 X406 is the time for the disposition specified in X407.</li> <li>5 X414 is the U.S. Customs and Border Protection (CBP) Facilities Information and Resource Management System (FIRMS) code or the Canadian Customs Sub-Location code.</li> <li>6 X417 reflects the time zone which the time reflects.</li> <li>7 X418 is the Customs port of final destination.</li> <li>8 X419 is the first foreign port of destination.</li> <li>9 X420 is the disposition code re-sent indicator. A 'Y' value indicates the disposition code is being resent due to a Port of Discharge or Vessel Name change. An 'N' value indicates there was no disposition code re-send required.</li> </ol>

**Notes:**

Elements X415 and X416 are used in the following 3 scenarios:

1. An ocean carrier discharges cargo in Canada and then turns it over to the railroad which assigns its SCAC to the bill and nominates the ocean carrier as an SNP. Therefore X415 will be 'OB' for ocean bill and X416 will be the bill of lading number.
2. The 'BN' reference number is the booking number provided in the inbound manifest.
3. The X411 and X412 Equipment Number elements will be returned for "Equipment -level" Status Notifications which are specific to a given Equipment for a Bill of Lading. When the X411 and X412 Equipment Number elements are not populated, then the Status Notification is assumed to apply to the entire Bill of Lading.

**Data Element Summary**

Ref.	Data				
	<u>Des.</u>	<u>Element</u>	<u>Name</u>	<u>Attributes</u>	
Must Use	X401	598	Bill of Lading/Waybill Number	O	1 AN 1/50
			Identification number assigned to the shipment by the carrier or consolidator		
			Bill Issuer Sequence Number. X409 + X401 comprise the unique bill of lading number		
Must Use	X402	380	Quantity	O	1 R 1/15
			Numeric value of quantity		
Not Used	X403	581	Customs Entry Type Code	X	1
Not Used	X404	601	Customs Entry Number	X	1 AN 1/50
M	X405	373	Date	M	1 DT 8/8
			Date expressed as CCYYMMDD where CC represents the first two digits of the calendar year		
			Date of Posting		
			CC		Century
			DD		Day of Month
			MM		Month of Year
			YY		Year
	X406	337	Time	X	1 TM 4/8
			Time expressed in 24-hour clock time as follows: HHMM, or HHMMSS, or		

HHMMSSD, or HHMMSSDD, where H = hours (00-23), M = minutes (00-59), S = integer seconds (00-59) and DD = decimal seconds; decimal seconds are expressed as follows: D = tenths (0-9) and DD = hundredths (00-99)

Time of Posting will be in Eastern Standard/Daylight time.

HH Hour  
MM Minute

M	X407	35	<b>Bill of Lading Disposition Code</b>	M	1 ID 2/3
Code indicating to a carrier or port authority about postings to a bill of lading					
A code advising the carrier, port authority, service bureau, or agent of the posting action taken on a bill of lading. Refer to Export Multimodal Manifest Appendix K.					
Not Used	X408	598	<b>Bill of Lading/Waybill Number</b>	X	1 AN 1/50
M	X409	140	<b>Standard Carrier Alpha Code</b>	M	1 ID 2/4
Code identifying the Standard Carrier Alpha Code					
SCAC of the bill issuer. X401 + X409 comprise the unique bill					
Of lading identifier.					
Not Used	X410	140	<b>Standard Carrier Alpha Code</b>	X	1 ID 2/4
	X411	206	<b>Equipment Initial</b>	O	1 AN 1/4
Prefix or alphabetic part of an equipment unit's identifying number					
	X412	207	<b>Equipment Number</b>	O	1 AN 1/15
Sequencing or serial part of an equipment unit's identifying number (pure numeric form for equipment number is preferred)					
	X413	310	<b>Location Identifier</b>	O	1 AN 1/30
Code which identifies a specific location					
CBP Port of Processing – Refer to Export Multimodal Manifest Appendix L					
CBP Uses only 4 numeric characters in this field.					
	X414	310	<b>Location Identifier</b>	O	1 AN 1/30
Code which identifies a specific location					
Facilities Information Resources Management Systems (FIRMS) code related to the location where the inspection is requested or the cargo is ready for inspection					
	X415	128	<b>Reference Identification Qualifier</b>	X	1 ID 2/3
Code identifying the Reference Identification					
Values provided by CBP.					
OB Ocean Bill of Lading					
FC Filer Code issued by Customs					
	X416	127	<b>Reference Identification</b>	X	1 AN 1/80
Reference information as defined for a particular Transaction Set or as specified by the Reference Identification Qualifier					
For Reference Identifier Qualifier "OB", the Reference Identifier is the Ocean bill of lading number.					
For Reference Identifier Qualifier "BN", the Reference Identifier is the Booking Number provided in the inbound manifest.					
Not Used	X417	623	<b>Time Code</b>	O	1 ID 2/2
Not Used	X418	310	<b>Location Identifier</b>	O	1 AN 1/30
	X419	310	<b>Location Identifier</b>	O	1 AN 1/30
Code which identifies a specific location					
Foreign Port of Destination. CBP displays 5 numeric characters in this field					
Not Used	X420	1073	<b>Yes/No Condition or Response Code</b>	O	1 ID 1/1

<b>Segment:</b>	<b>K1</b>	Remarks
<b>Position:</b>	0700	
<b>Loop:</b>	X4	Optional
<b>Level:</b>		
<b>Usage:</b>	Optional	
<b>Max Use:</b>	4	
<b>Purpose:</b>	To transmit information in a free-form format for comment or special instruction	
<b>Syntax Notes:</b>		
<b>Semantic Notes:</b>		
<b>Notes:</b>	Values provided by CBP.	

Data Element Summary				
Ref.	Data			
	<u>Des.</u>	<u>Element</u>	<u>Name</u>	<u>Attributes</u>
M	K101	61	Free-form Information Free-form information For inspection hold messages, CBP will provide instructions or contact information for the inspection in the free form text..	M 1 AN 1/30
Not Used	K102	61	Free-form Information	O 1 AN 1/30

<b>Segment:</b>	<b>N9</b>	<b>Extended Reference Information</b>
<b>Position:</b>	0710	
<b>Loop:</b>	X4	Optional
<b>Level:</b>		
<b>Usage:</b>	Optional	
<b>Max Use:</b>	999	
<b>Purpose:</b>	To transmit identifying information as specified by the Reference Identification Qualifier	
<b>Syntax Notes:</b>	<b>1</b> At least one of N902 or N903 is required. <b>2</b> If N906 is present, then N905 is required. <b>3</b> If either C04003 or C04004 is present, then the other is required. <b>4</b> If either C04005 or C04006 is present, then the other is required.	
<b>Semantic Notes:</b>	<b>1</b> N906 reflects the time zone which the time reflects. <b>2</b> N907 contains data relating to the value cited in N902.	
<b>Notes:</b>	Values will be returned if sent in the inbound message	

Data Element Summary					
Ref.	Data				
	<u>Des.</u>	<u>Element</u>	<u>Name</u>	<u>Attributes</u>	
M	N901	128	Reference Identification Qualifier	M	1 ID 2/3
			Code identifying the Reference Identification		
			Refer to Export Multimodal Manifest Appendix I		
M	N902	127	Reference Identification	X	1 AN 1/80
			Reference information as defined for a particular Transaction Set or as		
			specified by the Reference Identification Qualifier.		
			Refer to Export Multimodal Manifest Appendix I		
Not Used	N903	369	Free-form Description	X	1 AN 1/45
Not Used	N904	373	Date	O	1 DT 8/8
Not Used	N905	337	Time	X	1 TM 4/8
Not Used	N906	623	Time Code	O	1 ID 2/2
Not Used	N903	369	Free-form Description	X	1 AN 1/45
Not Used	N904	373	Date	O	1 DT 8/8
Not Used	N905	337	Time	X	1 TM 4/8
Not Used	N906	623	Time Code	O	1 ID 2/2

<b>Segment:</b>	<b>N7</b> Equipment Details
<b>Position:</b>	0810
<b>Loop:</b>	X4 Optional
<b>Level:</b>	
<b>Usage:</b>	Optional
<b>Max Use:</b>	999
<b>Purpose:</b>	To identify the equipment
<b>Syntax Notes:</b>	<ol style="list-style-type: none"> <li>1 If either N703 or N704 is present, then the other is required.</li> <li>2 If either N705 or N716 is present, then the other is required.</li> <li>3 If either N708 or N709 is present, then the other is required.</li> </ol>
<b>Semantic Notes:</b>	<ol style="list-style-type: none"> <li>1 N712 is the owner of the equipment.</li> <li>2 N723 is the operator or carrier of the rights of the equipment.</li> </ol>

#### Data Element Summary

	Ref.	Data		
	<u>Des.</u>	<u>Element</u>	<u>Name</u>	<u>Attributes</u>
Must Use	N701	206	<b>Equipment Initial</b> Prefix or alphabetic part of an equipment unit's identifying number Container Prefix from inboundmanifest	O 1 AN 1/4
M	N702	207	<b>Equipment Number</b> Sequencing or serial part of an equipment unit's identifying number (pure numeric form for equipment number is preferred) Container Number from inboundmanifest	M 1 AN 1/15
Not Used	N703	81	<b>Weight</b>	X 1 R 1/10
Not Used	N704	187	<b>Weight Qualifier</b>	X 1 ID 1/2
Not Used	N705	167	<b>Tare Weight</b>	X 1 N0 3/8
Not Used	N706	232	<b>Weight Allowance</b>	O 1 N0 2/6
Not Used	N707	205	<b>Dunnage</b>	O 1 N0 1/6
Not Used	N708	183	<b>Volume</b>	X 1 R 1/8
Not Used	N709	184	<b>Volume Unit Qualifier</b>	X 1 ID 1/1
Not Used	N710	102	<b>Ownership Code</b>	O 1 ID 1/1
Not Used	N711	40	<b>Equipment Description Code</b>	O 1 ID 2/2
Not Used	N712	140	<b>Standard Carrier Alpha Code</b>	O 1 ID 2/4
Not Used	N713	319	<b>Temperature Control</b>	O 1 AN 3/6
Not Used	N714	219	<b>Position</b>	O 1 AN 1/3
Not Used	N715	567	<b>Equipment Length</b>	O 1 N0 4/5
Not Used	N716	571	<b>Tare Qualifier Code</b>	X 1 ID 1/1
Not Used	N717	188	<b>Weight Unit Code</b>	O 1 ID 1/1
Not Used	N718	761	<b>Equipment Number Check Digit</b>	O 1 N0 1/1
Not Used	N719	56	<b>Type of Service Code</b>	O 1 ID 2/2
Not Used	N720	65	<b>Height</b>	O 1 R 1/8
Not Used	N721	189	<b>Width</b>	O 1 R 1/8
Not Used	N722	24	<b>Equipment Type Code</b>	O 1 ID 4/4
Not Used	N723	140	<b>Standard Carrier Alpha Code</b>	O 1 ID 2/4
Not Used	N724	301	<b>Car Type Code</b>	O 1 ID 1/4



**Segment:** **SE** Transaction SetTrailer  
**Position:** 1000  
**Loop:**  
**Level:**  
**Usage:** Mandatory  
**Max Use:** 1  
**Purpose:** To indicate the end of the transaction set and provide the count of the transmitted segments (including the beginning (ST) and ending (SE) segments)  
**Syntax Notes:**  
**Semantic Notes:**

Data Element Summary				
	Ref.	Data		
	<u>Des.</u>	<u>Element Name</u>	<u>Attributes</u>	
M	SE01	96 Number of Included Segments	M	1 N0 1/10
		Total number of segments included in a transaction set including ST and SE segments		
M	SE02	329 Transaction Set Control Number	M	1 AN 4/9
		Identifying control number that must be unique within the transaction set functional group assigned by the originator for a transaction set		

**Segment:** **GE** Functional Group Trailer  
**Position:** 1050  
**Loop:**  
**Level:**  
**Usage:** Mandatory  
**Max Use:** 1  
**Purpose:** To indicate the end of a functional group and to provide control information  
**Syntax Notes:**  
**Semantic Notes:** 1 The data interchange control number GE02 in this trailer must be identical to the same data element in the associated functional group header, GS06.

Data Element Summary				
Ref.	Data			
	<u>Des.</u>	<u>Element</u>	<u>Name</u>	<u>Attributes</u>
M	GE01	97	Number of Transaction Sets Included Total number of transaction sets included in the functional group or interchange (transmission) group terminated by the trailer containing this data element	M 1 N0 1/6
M	GE02	28	Group Control Number Assigned number originated and maintained by the sender	M 1 N0 1/9

**Segment:** **IEA** Interchange Control Trailer  
**Position:** 1100  
**Loop:**  
**Level:**  
**Usage:** Mandatory  
**Max Use:** 1  
**Purpose:** To define the end of an interchange of zero or more functional groups and interchange-related control segments  
**Syntax Notes:**  
**Semantic Notes:**

Data Element Summary				
Ref.	Data			
	<u>Des.</u>	<u>Element</u>	<u>Name</u>	<u>Attributes</u>
M	IEA01	I16	Number of Included Functional Groups A count of the number of functional groups included in an interchange	M 1 N0 1/5
M	IEA02	I12	Interchange Control Number A control number assigned by the interchange sender	M 1 N0 9/9